


# roboRIO Team Number Setter / roboRIO 队伍编号设置工具



The roboRIO Team Number Setter is a cross-platform utility that can be used to set the team number on the roboRIO. It is an alternative to the roboRIO imaging tool for setting the team number.

roboRIO Team Number Setter 是一款跨平台工具，可用于设置 roboRIO 上的队伍编号。设置队伍编号时，它可以替代 roboRIO Imaging Tool。

In Visual Studio Code, press **Ctrl+Shift+P** and type **WPILib** or click the WPILib logo in the top right to launch the WPILib Command Palette. Select Start Tool, then select roboRIOTeamNumberSetter.

在 Visual Studio Code 中，按 **Ctrl+Shift+P** 并输入 **WPILib**，或者点击右上角的 WPILib 标志，以打开 WPILib Command Palette。选择 Start Tool，然后选择 roboRIOTeamNumberSetter。

## Note / 说明

The desktop shortcut for the roboRIO Team Number Setter doesn't work in WPILib release 2026.1.1. However, the instructions above for starting the tool from VS Code and the start menu shortcut work. See [Known Issues](#).

在 WPILib 2026.1.1 版本中，roboRIO Team Number Setter 的桌面快捷方式无法使用。不过，上述从 VS Code 启动该工具的方法以及开始菜单中的快捷方式均可使用。请参阅 [Known Issues / 已知问题](#)。

Connect to the roboRIO over USB to use the tool, as this is the simplest method when the team number hasn't been set.

使用该工具时，请通过 USB 连接 roboRIO，因为在尚未设置队伍编号时，这是最简单的连接方式。

## Setting Team Number / 设置队伍编号

Enter your team number in the Team Number field and select Set team to xxxx. This will take about a second, then press the Reboot button to reboot the roboRIO so the new team number takes effect.

在 Team Number 字段中输入队伍编号，然后选择 Set team to xxxx。此操作大约需要一秒钟；随后按下 Reboot 按钮重启 roboRIO，使新的队伍编号生效。

## Enabling/Disabling Webserver / 启用或禁用 Web 服务器

The roboRIO's [webserver](#) provides some debugging and enables some configuration. However, it also takes memory away from the robot program. You can disable it by clicking on the Disable Web Server button. If you'd like to enable it again, you can click Enable Web Server.

### roboRIO 的 Web

[服务器](#)提供一些调试功能，并允许进行某些配置。不过，它也会占用机器人程序可用的内存。你可以点击 Disable Web Server 按钮禁用它。如果想重新启用，可以点击 Enable Web Server。

#### Warning / 警告

the Imaging Tool will not be able to connect to the roboRIO when the Web Server is disabled.

禁用 Web Server 后，Imaging Tool 将无法连接到 roboRIO。

## roboRIO Identification / 识别 roboRIO

Clicking the Blink button will cause the roboRIO's Radio LED to blink a few times to help identify the roboRIO.

点击 Blink 按钮会使 roboRIO 的 Radio LED 闪烁数次，以帮助识别该 roboRIO。